OnBarcode.com Java Barcode Reader

Developer Guide

Table of Contents

Barcode.com Java Barcode Reader	. 1
veloper Guide	. 1
Overview	. 2
Install & Requirements	. 3
Quick to Start	. 4
FAQ:	. 5
Scan multiple barcodes from the image documents	. 5
2. Scan barcodes from .NET image object	. 5
3. Scan barcodes from the defined area within the image	. 5
4. Scan maximum 1 barcode from the image	. 6
5. Scan and get more information about the barcode	. 6

Overview

UPC-A UPC-E

Java Barcode Reader is a Java library which scans and recognizes barcodes from image files. You can easily embed barcode recognition features in your Java projects.

All Java Barcode Reader Supporting Bar Code Types

1D / Linear Barcodes 2D / Matrix Barcod	des
Codabar Data Matrix	
Code 39	
Code 128 PDF-417	
EAN-8	
EAN-13 QR Code	
Identcode	
Interleaved 2 of 5	
ISBN	
ISSN	
ITF-14	
Leitcode	

Install & Requirements

Requirement

You need Java JDK 1.4.2 or later version.

<u>Install</u>

Put **OnBarcode.BarcodeReader.jar** into your Java project classpath.

To read Tiff and bitmap image, you need two extra jars from Sun Microsystem, see how to read barcodes from tiff and bitmap images.

Quick to Start

Note:

In trial version, the <u>first character</u> return in barcode data is <u>randomly generated</u>. In production version, it will return correct character.

Read barcodes from image is a simple task with barcode reader for java library.

Here is the sample code.

String[] barcodes = BarcodeScanner.Scan("code39image.gif", BarcodeType.Code39);

Pass your barcode image file, and barcode type to BarcodeScanner, and it will return barcode datas.

FAQ:

1. Scan multiple barcodes from the image documents

String[] barcodes = BarcodeScanner.Scan("code39image.gif", BarcodeType.Code39);

2. Scan barcodes from .NET image object

java.awt.image.RenderedImage objImage = ...; String[] barcodes = BarcodeScanner.Scan(objImage, BarcodeType.Code39);

3. Scan barcodes from the defined area within the image

ArrayList areas = new ArrayList(); SRegion area = new SRegion(0, 0, 50, 60); areas.add(area); String[] barcodes = BarcodeScanner.ScanRegions("code39image.gif", BarcodeType.Code39, areas);

4. Scan maximum 1 barcode from the image

String[] barcodes = BarcodeScanner.ScanSingleBarcode("code39image.gif", BarcodeType.Code39);

5. Scan and get more information about the barcode

 $\label{eq:barcodeDetail} BarcodeDetail[] \ barcodeDetails = BarcodeScanner.ScanInDetails("code39image.gif", BarcodeType.Code39);$